

How to translate dtl to csv file

1. After users get the *.dtl file from HMI, open Project Manager and press EasyConverter

炎 Project Manager						
– HMI IP, Password – Type : MT6000/800	0 i Series 💌					
Settings Reboot HMI						
Connection						
O Ethernet O USB cable (i series only)						
- Editor						
EasyBui	lder 8000					
EasyCo	onverter					
EasyPrinter						
Recipe/Extended	Recipe/Extended Memory Editor					
EasyAddressViewer						
Build Download Data for CF/ USB Disk						
_ Transfer						
Download	Upload					
Simulation						
On-line Simulation	Off-line Simulation					
Pass-through Pass-through						
Help	[Exit					

2. Select Open file and choose the desired *.dtl file from your pc.

🕮 Untitled - EasyConverter
1File Edit View Help
? 🗙
🔁 Voltage 🕥 🍞 😥 🖬 🗸
20071204.dtl
20071205.dtl 2. 20071206.dtl



3. Press OK for reading the *.dtl file.

No	Name	Туре	Word Size	Digits	Scaling	
1		16-bit Unsigned	1	0	No	•
2		16-bit Unsigned	1	0	No	•
3		16-bit Unsigned	1	0	No	•
4		16-bit Unsigned	1	0	No	•
5		16-bit Unsigned	1	0	No	•
-						
	caling &	Offset				



4. Press "EXCEL" icon to translate the file.

👺 K:\Voltage\20071206.dtl - EasyConverter
<u>File E</u> dit <u>V</u> iew <u>H</u> elp
[Creation time]
Thu Dec 06 11:10:48 2007
[Data]
Time, , , , , , , ,
11:10:48,52,44,81,31,41
11:10:49,52,44,81,31,41
11:10:50,52,44,81,31,41
11:10:51,52,44,81,31,41
11:10:52,52,44,81,31,41
11:10:53,52,44,81,31,41
11:10:54,52,44,81,31,41
11:10:55,52,44,81,31,41
11:10:56,52,44,81,31,41
11:10:57,52,44,81,31,41
11:10:58,52,44,81,31,41
11:10:59,52,44,81,31,41
11:11:00,52,44,81,31,41
11:11:01,52,44,81,31,41
11:11:02.52.44.81.31.41

5. The *.dtl file will be translated to *.csv file by Excel.

	А	В	С	D	E	F		
1	[Creation ti	me]						
2	Thu Dec 06 11:10:48 2007							
3	[Data]							
4	Time							
5	11:10:48	52	44	81	31	41		
6	11:10:49	52	44	81	31	41		
7	11:10:50	52	44	81	31	41		
8	11:10:51	52	44	81	31	41		
9	11:10:52	52	44	81	31	41		
10	11:10:53	52	44	81	31	41		
11	11:10:54	52	44	81	31	41		
12	11:10:55	52	44	81	31	41		
13	11:10:56	52	44	81	31	41		
14	11:10:57	52	44	81	31	41		
15	11:10:58	52	44	81	31	41		
16	11:10:59	52	44	81	31	41		
• •	< < ▶ H\ <u>20071206</u> /							